

PowerDNS Cloud Control

Reference

Apr 06, 2023

Release 2.3.0-ALPHA3

©2023 by Open-Xchange AG and PowerDNS.COM BV. All rights reserved. Open-Xchange, PowerDNS, the Open-Xchange logo and PowerDNS logo are trademarks or registered trademarks of Open-Xchange AG. All other company and/or product names may be trademarks or registered trademarks of their owners. Information contained in this document is subject to change without notice.

Contents

1	Overview	1
2	Registry configuration	2
3	Cluster networking	3
3.1	IPv4 only (default)	3
3.2	IPv6 only	3
3.3	Dualstack - IPv4 primary	4
3.4	Dualstack - IPv6 primary	4
4	Exposing dnsdist	5
4.1	Example: Exposing via NodePort	6
4.2	Example: Exposing via LoadBalancer	7
4.3	Example: Exposing via LoadBalancer with mixed protocols	8
4.4	Example: Separate LoadBalancers for IPv4 & IPv6 in a dualstack cluster	8
5	Exposing auth API	10
6	Labels & Annotations	12
6.1	Labeling services with multiple ports	13
6.2	Precedence of labeling & annotating	14
7	Security contexts	15
7.1	Configuring a global Pod security context	15
7.2	Configuring a Pod security context for a specific set of instances	16
7.3	Precedence of podSecurityContext	16
8	Default configuration	17
8.1	auth	17
8.2	dnsdist	19
8.3	recursor	23
8.4	resolver	25
8.5	zoneControl	25
9	Instances	26
9.1	auths	26
9.1.1	Parameters	26
9.1.2	Parameter Sets	26
9.1.3	Backends	29
9.1.3.1	Postgres (pre-existing)	29
9.1.3.2	Postgres (Operator-managed)	30
9.1.3.3	MySQL	30
9.1.3.4	GeoIP	31

9.1.3.5	GeoIP - MaxMind Database	31
9.1.3.6	GeoIP - MaxMind Database - HTTP	31
9.1.3.7	GeoIP - MaxMind Database - OCI	32
9.1.3.8	GeoIP - Custom Database	33
9.1.3.9	LightningStream	34
9.2	dnsdists	38
9.2.1	Parameters	39
9.2.2	Parameter Sets	39
9.2.3	Server Pools	43
9.2.4	DNS over HTTP(S)	44
9.2.5	DNS over TLS	46
9.3	recursors	47
9.3.1	Parameters	47
9.3.2	Parameter Sets	47
9.3.3	Forward Zones	49
9.4	resolvers	50
9.4.1	Parameters	50
9.4.2	Parameter Sets	50
9.5	rulesets	51
9.5.1	Rules	52
9.5.2	Combinators	52
9.5.3	Selectors	53
9.5.3.1	TCP	53
9.5.3.2	MaxQPS	53
9.5.3.3	MaxQPSIP	53
9.5.3.4	NetmaskGroup	54
9.5.3.5	Opcode	54
9.5.3.6	QName	55
9.5.3.7	QType	55
9.5.4	Actions	55
9.5.4.1	Allow	55
9.5.4.2	Drop	55
9.5.4.3	Pool	56
9.5.4.4	QPS	56
9.5.4.5	RCode	56
9.5.4.6	TC	56
9.6	zonecontrols	56
9.6.1	Parameters	57
9.6.2	Parameter Sets	57
9.6.3	Postgres Database	57
9.6.3.1	Postgres (pre-existing)	58
9.6.3.2	Postgres (Operator-managed)	58

10 Prometheus

59

1 Overview

Configuration of a deployment can be achieved by overriding specific values that are exposed by the Helm chart. This reference guide lists all the values that can be set/configured. Since there are many different configuration options available, these have been separated into the following sections inside the helm values:

Generic configuration:

- **global**: Overrides to pull images from a private registry
- **registrySecrets**: Configuration of credentials for the image registry
- **ipFamily**: Configuration of the cluster networking
- **prometheus**: Configuration of Prometheus scrape settings

Configuration of default settings:

- **auth**: Default configuration for all auth instances
- **dnsdist**: Default configuration for all dnsdist instances
- **recursor**: Default configuration for all recursor instances
- **resolver**: Default configuration for all resolver instances
- **zonecontrol**: Default configuration for all zonecontrol instances

Configuration of instances:

- **auths**: Collection of auth instances to deploy
- **dnsdists**: Collection of dnsdist instances to deploy
- **recursors**: Collection of recursor instances to deploy
- **resolvers**: Collection of resolver instances to deploy
- **rulesets**: Sets of rules to deploy, for dnsdist to use
- **zonecontrols**: Collection of zonecontrol instances to deploy

Each of these sections is explained in detail in the chapters below.

For a basic example of how to use the values, please refer to the *Getting Started* chapter in the *Overview* guide.

2 Registry configuration

All images referenced are stored on a registry at registry.open-xchange.com. To ensure the images can be pulled you need to provide the corresponding registry's credentials. This can be done in the following block in the helm values (replace the username & password accordingly):

```
registrySecrets:  
  registry: registry.open-xchange.com  
  username: REGISTRY_USERNAME_HERE  
  password: REGISTRY_PASSWORD_HERE  
  email: user@some.domain.com
```

If you intend to run the monitoring stack on a kubernetes cluster which makes use of a local/private registry, you can use one or more of the following settings in your helm values to configure that registry:

```
# Monitoring - global overrides  
global:  
  # Override image-related settings for this chart and all subcharts  
  image:  
    # Override registry for all images  
    registry: "myregistry.local:8085"  
  
    # Override repository for all images  
    repository: "myrepository"  
  
    # Override pullPolicy for all images  
    pullPolicy: "IfNotPresent"
```

Each setting explained:

global.image.registry

All images will be attempted to be pulled from this registry (format: host:port)

global.image.repository

All images will be attempted to be pulled from this repository, on above configured registry

global.image.pullPolicy

This pull policy will be specified for each image

If you have a need to override the above settings for specific images, you can find the corresponding 'image:' configuration blocks in the helm values file.

3 Cluster networking

To be able to support Kubernetes clusters with IPv4, IPv6 or dual stack (IPv4 & IPv6) configurations, it is required to ensure the 'ipFamily' configuration in the helm values matches your cluster. The 'ipFamily' section contains the following parameters:

- **ipFamily.ipv4**: Whether or not your cluster has IPv4 enabled (Default: true)
- **ipFamily.ipv6**: Whether or not your cluster has IPv6 enabled (Default: false)
- **ipFamily.families**: Preference of IP families on your cluster, if it is a dualstack cluster

To ensure your deployment is correctly configured, you need to provide one of the 4 possible variations:

3.1 IPv4 only (default)

```
# Networking configuration
ipFamily:
  ipv4: true
  ipv6: false
  families:
    - "IPv4"
    - "IPv6"
```

Note: 'families' is ignored in this configuration. It is only used in a dualstack setup.

3.2 IPv6 only

```
# Networking configuration
ipFamily:
  ipv4: false
  ipv6: true
  families:
    - "IPv4"
    - "IPv6"
```

Note: 'families' is ignored in this configuration. It is only used in a dualstack setup.

3.3 Dualstack - IPv4 primary

If you are running a dualstack cluster, you can check any Pod to see if your cluster has a preference for IPv4 or IPv6. Your pods will have a 'podIP' and 2 values for 'podIPs'. If the 'podIP' is an IPv4 address as shown in the example below, then you are running a cluster with IPv4 as primary:

```
podIP: 172.17.183.4 # IPv4
podIPs:
- ip: 172.17.183.4 # IPv4
- ip: fd43:128b:8658:b73b:3eb7:2e30:8815:3f6 # IPv6
```

Configuration for dualstack with IPv4 primary:

```
# Networking configuration
ipFamily:
  ipv4: true
  ipv6: true
families:
- "IPv4" # IPv4 is primary
- "IPv6"
```

3.4 Dualstack - IPv6 primary

If you are running a dualstack cluster, you can check any Pod to see if your cluster has a preference for IPv4 or IPv6. Your pods will have a 'podIP' and 2 values for 'podIPs'. If the 'podIP' is an IPv6 address as shown in the example below, then you are running a cluster with IPv6 as primary:

```
podIP: fd43:128b:8658:b73b:3eb7:2e30:8815:3f6 # IPv6
podIPs:
- ip: fd43:128b:8658:b73b:3eb7:2e30:8815:3f6 # IPv6
- ip: 172.17.183.4 # IPv4
```

Configuration for dualstack with IPv6 primary:

```
# Networking configuration
ipFamily:
  ipv4: true
  ipv6: true
families:
- "IPv6" # IPv6 is primary
- "IPv4"
```

4 Exposing dnssdist

By default a set of dnssdist instances will have a Service object created with type ClusterIP. The default configuration is as follows (Values: dnssdist.service):

```
service:
  type: ClusterIP
  ports:
    udp:
      port: 53
      protocol: UDP
    tcp:
      port: 53
      protocol: TCP
```

The above results in a Service object with UDP & TCP listeners on port 53. To modify the default service, you can specify a *service* item in the dnssdist instance, such as:

```
dnssdists:
  mydnssdist:
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: myrecursor
        packetcache:
          maxEntries: 200000
    service:
      type: NodePort
```

This will override the type of the Service object from *ClusterIP* to *NodePort*.

Available parameters:

- type
- loadBalancerIP (Only applicable if type = LoadBalancer)
- loadBalancerSourceRanges (Only applicable if type = LoadBalancer)
- loadBalancerClass (Only applicable if type = LoadBalancer)
- lbMixedProtocol (Only applicable if type = LoadBalancer)
- lbPerIPFamily (Only applicable if type = LoadBalancer)
- clusterIP
- clusterIPs
- externalIPs

- externalName
- externalTrafficPolicy
- internalTrafficPolicy
- sessionAffinity
- healthCheckNodePort
- sessionAffinityConfig
- labels

These parameters directly expose Kubernetes' configuration equivalents, for their usage & accepted values please refer to: <https://kubernetes.io/docs/reference/kubernetes-api/service-resources/service-v1/>

4.1 Example: Exposing via NodePort

To expose dnsmdist via a NodePort, you can specify the appropriate type. In this example, both UDP & TCP will be exposed via a NodePort, where the NodePort will be randomly selected from the node-port range:

```
dnsdists:  
  mydnsdist:  
    replicas: 2  
    pools:  
      default:  
        serverGroups:  
          - group: myrecursor  
        packetcache:  
          maxEntries: 200000  
    service:  
      type: NodePort
```

You can also specify the NodePort which you want to use, for example:

```
dnsdists:  
  mydnsdist:  
    replicas: 2  
    pools:  
      default:  
        serverGroups:  
          - group: myrecursor  
        packetcache:  
          maxEntries: 200000  
    service:  
      type: NodePort  
      ports:  
        udp:  
          port: 53  
          protocol: UDP  
          nodePort: 30053  
        tcp:  
          port: 53
```

(continues on next page)

(continued from previous page)

```
protocol: TCP
nodePort: 30053
```

4.2 Example: Exposing via LoadBalancer

To expose dnsmdist via a LoadBalancer, you can specify the appropriate type. When 'LoadBalancer' is configured as type, it will create the default ClusterIP Service + 1 LoadBalancer Service for each specified port. This is done to satisfy a Kubernetes constraint regarding LoadBalancer objects when multiple protocols are requested.

In this example, both the default UDP & TCP ports will be exposed via a LoadBalancer Service (MetalLB annotation provided as example, substitute with annotations required by your LoadBalancer provider) on port 53:

```
dnsdists:
  mydnsmdist:
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: myrecursor
        packetcache:
          maxEntries: 200000
    service:
      type: LoadBalancer
      annotations:
        metallb.universe.tf/address-pool: name_of_pool
```

If necessary, you can also request a specific LoadBalancer IP, as shown in the following example:

```
dnsdists:
  mydnsmdist:
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: myrecursor
        packetcache:
          maxEntries: 200000
    service:
      type: LoadBalancer
      annotations:
        metallb.universe.tf/address-pool: name_of_pool
      loadBalancerIP: 12.34.56.78
```

4.3 Example: Exposing via LoadBalancer with mixed protocols

By default, a separate LoadBalancer service will be created per protocol (tcp & udp for dnssdist). If your cluster has the 'MixedProtocolLBService' feature gate enabled you can force a single LB to be created with both protocols using the 'lbMixedProtocol' flag:

```
dnsdists:
  mydnsdist:
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: myrecursor
        packetcache:
          maxEntries: 200000
    service:
      type: LoadBalancer
      lbMixedProtocol: true
```

4.4 Example: Separate LoadBalancers for IPv4 & IPv6 in a dualstack cluster

If you run a dualstack cluster, you can opt to have a separate LoadBalancer created for each IP family (IPv4 & IPv6). This can be done using the 'lbPerIPFamily' flag:

```
dnsdists:
  mydnsdist:
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: myrecursor
        packetcache:
          maxEntries: 200000
    service:
      type: LoadBalancer
      lbPerIPFamily: true
```

This will create 4 LoadBalancer services, namely:

- TCP-IPv4
- UDP-IPv4
- TCP-IPv6
- UDP-IPv6

If your cluster has the 'MixedProtocolLBService' feature gate enabled, you can use the 'lbMixedProtocol' flag to have this reduced to an IPv4 LoadBalancer and an IPv6 LoadBalancer, each with both TCP & UDP supported:

```
dnsdists:
  mydnsdist:
```

(continues on next page)

(continued from previous page)

```
replicas: 2
pools:
  default:
    serverGroups:
      - group: myrecursor
    packetcache:
      maxEntries: 200000
service:
  type: LoadBalancer
  lbMixedProtocol: true
  lbPerIPFamily: true
```

5 Exposing auth API

By default a set of auth instances will not have an Ingress object created. If you wish to expose auth's API you can do so by configuring the Ingress object.

Note: We highly recommend providing the necessary stickiness annotations to any created Ingress object. Below examples include nginx stickiness annotations, please use your ingress controller's corresponding equivalents if using a different ingress controller.

For these examples we will assume the following auth instance is to be exposed:

```
auths:
  myauth:
    replicas: 2
```

If the above is deployed, 2 replicas of auth will be created, but no Ingress object will exist. To add an Ingress, use the following additional config:

```
auths:
  myauth:
    replicas: 2
    api:
      ingress:
        ingressClassName: Name of the Ingress Class - omit this if you wish to use the
        ↪ default Ingress Class or prefer to use the deprecated method of using annotations
        enabled: true
        annotations:
          <Annotations required by your Ingress controller>
        hosts:
          - <Hosts on which to have the Ingress listen>
      tls:
        - secretName: <Secret containing certificates - if HTTPS is desired>
          hosts:
            - <Hosts for which HTTPS is desired>
```

Example for plain HTTP using *nginx* Ingress Controller for host *myhost.mydomain.com* using the *ingressClassName nginx*:

```
auths:
  myauth:
    replicas: 2
    api:
      ingress:
        enabled: true
        ingressClassName: nginx
        annotations:
          nginx.ingress.kubernetes.io/affinity: "cookie"
```

(continues on next page)

(continued from previous page)

```
nginx.ingress.kubernetes.io/session-cookie-name: "ccroute"  
nginx.ingress.kubernetes.io/session-cookie-expires: "172800"  
nginx.ingress.kubernetes.io/session-cookie-max-age: "172800"  
hosts:  
- myhost.mydomain.com
```

Example for HTTPS using *nginx* Ingress Controller & certificates generated into a secret named *auth-api-certs* by a cert-manager cluster issuer named *letsencrypt-prod* on host *myhost.mydomain.com*:

```
auths:  
  myauth:  
    replicas: 2  
    api:  
      ingress:  
        enabled: true  
        ingressClassName: nginx  
        annotations:  
          nginx.ingress.kubernetes.io/affinity: "cookie"  
          nginx.ingress.kubernetes.io/session-cookie-name: "ccroute"  
          nginx.ingress.kubernetes.io/session-cookie-expires: "172800"  
          nginx.ingress.kubernetes.io/session-cookie-max-age: "172800"  
          cert-manager.io/cluster-issuer: letsencrypt-prod  
        hosts:  
        - myhost.mydomain.com  
      tls:  
        - secretName: auth-api-certs  
          hosts:  
          - myhost.mydomain.com
```

6 Labels & Annotations

To add labels & annotations to objects you can use several layers of configuration. To add labels & annotations to all pods or services you can use the following top-level configuration items:

- **podAnnotations:** Annotations to be added to each Pod (default: `{}`)
- **podLabels:** Labels to be added to each Pod (default: `{}`)
- **serviceLabels:** Labels to be added to each Service object (default: `{}`)

Alternatively, you can also add labels & annotations to all instances of a specific type, for example:

```
# Labels on dnsmdist pods & services
dnsmdist:
  podLabels:
    mylabel: label_value
  serviceLabels:
    mylabel: label_value

# Annotations on Auth pods
auth:
  podAnnotations:
    my.example.com/annotation: annotation_value
    my.example.com/moreannotations: another_value

# Labels on Recursor services
recursor:
  serviceLabels:
    mylabel: label_value
```

Or you can add labels & annotations specifically to a set of instances, for example:

```
# dnsmdist instances with pod & service labels
dnsmdists:
  mydnsmdist:
    podLabels:
      mylabel: my_value
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: myrecursor
    service:
      labels:
        my_service_label: some_value
        another_label: another_value
```

(continues on next page)

(continued from previous page)

```
# Recursor instances with annotations
recursors:
  myrecursor:
    podAnnotations:
      my.example.com/anno1: annotation_value
      my.example.com/anno2: another_value
    replicas: 2
```

6.1 Labeling services with multiple ports

There are 2 types of service configurations which can lead to the creation of multiple service objects for the same set of instances, namely:

- Services of type: *LoadBalancer*
- Services with: *servicePerPort: true*

To give both service objects the same labels you can use the above documented *labels:* configuration item on the parent *service:* item.

However, if you wish to configure different labels for each of these services, you can go one step further and define the labels for each port, for example:

```
# dnsmdist instances with pod & service labels
dnsmdists:
  mydnsmdist:
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: recursor
    service:
      labels:
        service.label/generic: some_value
      type: LoadBalancer
      externalTrafficPolicy: Local
      ports:
        udp:
          labels:
            service.label/udp: udp_label_value
        tcp:
          labels:
            service.label/tcp: tcp_label_value
```

This will lead to the following labels on each service:

- dnsmdist-mydnsmdist-lb-tcp: Has labels *service.label/generic* & *service.label/tcp*
- dnsmdist-mydnsmdist-lb-udp: Has labels *service.label/generic* & *service.label/udp*

6.2 Precedence of labeling & annotating

Since you can add labels & annotations at multiple levels, it is important to understand the order of precedence. In CloudControl, the order is as follows:

(for Services: Port-specific labels) > Instance-specific labels/annotations > Instance-type labels/annotations > top-level labels/annotations

The precedence is only used to pick a label/annotation value if the exact name of a label/annotation is defined at multiple levels. If labels/annotations are defined at different levels with different names, they are all added to the final set of labels/annotations on an object.

7 Security contexts

By default Cloud Control deploys all Pods with the following security context:

```
podSecurityContext:
  fsGroup: 953
  runAsUser: 953
  runAsGroup: 953
```

And all containers have the following applied:

```
securityContext:
  readOnlyRootFilesystem: true
  allowPrivilegeEscalation: false
```

The *podSecurityContext* can be overwritten on a specific set of instances or globally for all Pods deployed as part of Cloud Control. The *securityContext* placed on each container within a Pod is not configurable as they help safeguard against potential vulnerabilities.

7.1 Configuring a global Pod security context

To overwrite the *podSecurityContext* for all instances you can add a *podSecurityContext* at the top-level:

```
podSecurityContext:
  runAsUser: 1000953

dnsdists:
  mydnsdist:
    replicas: 2
    pools:
      default:
        serverGroups:
          - group: myrecursor

recursors:
  myrecursor:
    replicas: 2
```

Since the configuration of this *podSecurityContext* overwrites the full default *podSecurityContext*, this leads to the following differences compared to the defaults:

- *fsGroup* - This is no longer present, so it is dropped from the security context
- *runAsUser* - This is now set to '1000953'

- `runAsGroup` - This is no longer present, so it is dropped from the security context

Notes:

- When overriding the `podSecurityContext`, make sure you always specify a `runAsUser` or have your platform assign one automatically
- Any field supported by Kubernetes in a Pod-level `securityContext` can be configured here

7.2 Configuring a Pod security context for a specific set of instances

To overwrite the `podSecurityContext` for a set of instances you can add a `podSecurityContext` on the instance level:

```
recursors:  
  myrecursor:  
    replicas: 2  
    podSecurityContext:  
      runAsUser: 1000953
```

7.3 Precedence of podSecurityContext

Since you can configure `podSecurityContext` at multiple levels, it is important to understand the order of precedence. In CloudControl, the order is as follows:

Instance-specific `podSecurityContext` > top-level `podSecurityContext` > default `podSecurityContext`

Note: The `podSecurityContext` configurations are not merged into each other. If you specify a `podSecurityContext` on an instance it will fully replace a `podSecurityContext` of lower precedence.

8 Default configuration

8.1 auth

Default settings for all auth instances, configurable under 'auth' in helm values.

- **affinity**: Kubernetes pod affinity (default: *{}*)
- **antiAffinityPreset**: Pod anti affinity, if *affinity* is not set (default: *preferred*)
- **apiKey**: API key used to access the /api endpoint, used to configure a static key (default: generated and stored in a secret)
- **metricsPath**: Path on which Prometheus metrics will be served (default: */metrics*)
- **metricsPort**: Port on which Prometheus metrics will be served (default: *8082*)
- **nodeSelector**: Kubernetes pod nodeSelector (default: *{}*)
- **podAnnotations**: Annotations to be added to each Pod
- **podLabels**: Labels to be added to each Pod
- **serviceLabels**: Labels to be added to each Service object (default: *{}*)
- **readinessFailureThreshold**: When a probe fails, Kubernetes will try this many times before marking the container as Unready. Updates deployment, resulting in respawn of recursor pods (default: *2*)
- **readinessInitialDelaySeconds**: Number of seconds after the containers have started before readiness probes are initiated. Updates deployment, resulting in respawn of recursor pods. (default: *5*)
- **readinessPeriodSeconds**: How often (in seconds) to perform the readiness probes. Updates deployment, resulting in respawn of recursor pods (default: *2*)
- **readinessStateProbeInterval**: How often (in seconds) the agent will judge the health state of the recursor agent. (default: *2*)
- **readinessSuccessThreshold**: Minimum consecutive successful probes before a container is marked Ready. Updates deployment, resulting in respawn of recursor pods (default: *2*)
- **readinessTimeoutSeconds**: Number of seconds after which the readiness probes time out. Updates deployment, resulting in respawn of recursor pods (default: *1*)
- **replicas**: Default number of replicas in a recursor deployment (default: *2*)
- **webserverACLAllowAll**: Allow all inbound traffic to auth webserver, regardless of source IP (default: *true*)

- **webserverACL**: Netmasks to allow webserver traffic from (default: `127.0.0.1/32, 192.168.0.0/16, 10.0.0.0/8, 172.16.0.0/12, ::1, fc00::/7`)
- **webserverPassword**: Instead of generating a password for the webserver, set a static one (default: generated and stored in a secret)
- **hpa**: (Horizontal Pod Autoscaler defaults)
 - **enabled**: Enable or disable the HPA (default: `false`)
 - **minReplicas**: Minimum # of replicas (default: 2)
 - **maxReplicas**: Maximum # of replicas (default: 4)
 - **metrics**: Metric(s) upon which to make decisions regarding scaling. Must be an array of MetricSpec (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#metricspec-v2beta2-autoscaling>). Examples are in the helm values.
 - **behavior**: Behavior of the HPA, must be instance of HorizontalPodAutoscalerBehavior (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#horizontalpodautoscalerspec-v2beta2-autoscaling>).
- **agentResources**: (auth agent resource allocation defaults)
 - **limits**: (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests**: (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)
- **resources**: (auth resource allocation defaults)
 - **limits**: (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests**: (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)
- **lightningStreamResources**: (LightningStream resource allocation defaults)
 - **limits**: (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests**: (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)
- **lightningStream**: (LightningStream defaults)

- **logLevel**: Loglevel for LightningStream containers (default: *info*, available options: *debug, info, warning, error, fatal*)

8.2 dnsmdist

Default settings for all dnsmdist instances, configurable under 'dnsmdist' in helm values.

- **aclAdd**: Netmasks allowed to access dnsmdist, in addition to the loopback, RFC1918 and other local addresses. Only applicable if `aclAllowAll` is *false* (default: `[]`)
- **aclAllowAll**: Allow all inbound traffic to dnsmdist, regardless of source IP. (default: *true*)
- **affinity**: Kubernetes pod affinity (default: `{}`)
- **antiAffinityPreset**: Pod anti affinity, if *affinity* is not set (default: *preferred*)
- **consistentHashingBalancingFactor**: Set the maximum imbalance between the number of outstanding queries intended for a given server, based on its weight, and the actual number, when using the chashed consistent hashing load-balancing policy. Default is 0, which disables the bounded-load algorithm. (default: 0)
- **do53Locals**: Default amount of Do53 listen sockets per dnsmdist pod (default: 1)
- **do53TcpFastOpenQueueSize**: Default size of the TCP Fast Open queue on Do53 listen sockets (Dnsmdist default)
- **do53TcpListenQueueSize**: Default size of the listen queue on Do53 listen sockets (Dnsmdist default)
- **dohLocals**: Default amount of listen sockets per DoH listener (default: 1)
- **dotLocals**: Default amount of listen sockets per DoT listener (default: 1)
- **metricsPath**: Path on which Prometheus metrics will be served (default: `/metrics`)
- **metricsPort**: Port on which Prometheus metrics will be served (default: 8082)
- **nodeSelector**: Kubernetes pod nodeSelector (default: `{}`)
- **podAnnotations**: Annotations to be added to each Pod
- **podLabels**: Labels to be added to each Pod
- **podSecurityContext**: Kubernetes Pod security context (default: 953 as fsGroup, runAsUser & runAsGroup)
- **port**: Port on which dnsmdist will listen for Do53 traffic (default: 5353)
- **readinessDo53ProbeInterval**: How often (in seconds) the agent will judge the health state of dnsmdist via tests against the Do53 listeners. (default: 2)
- **readinessDo53QDomain**: Domain used in the query to judge whether the Do53 listeners of a dnsmdist container are healthy and ready for traffic. (default: *a.root-servers.net*)
- **readinessDo53QTimeout**: Number of seconds after which the query used to judge whether the Do53 listeners of a dnsmdist container are healthy and ready for traffic time out. (default: 1)
- **readinessDo53QType**: Type of query used to judge whether the Do53 listeners of a dnsmdist container are healthy and ready for traffic. (default: A)

- **readinessFailureThreshold:** When a probe fails, Kubernetes will try this many times before marking the container as Unready. Updates deployment, resulting in respawn of dnssdist pods (default: 2)
- **readinessInitialDelaySeconds:** Number of seconds after the containers have started before readiness probes are initiated. Updates deployment, resulting in respawn of dnssdist pods. (default: 5)
- **readinessPeriodSeconds:** How often (in seconds) to perform the readiness probes. Updates deployment, resulting in respawn of dnssdist pods (default: 2)
- **readinessStateProbeInterval:** How often (in seconds) the agent will judge the health state of the dnssdist agent. (default: 2)
- **readinessSuccessThreshold:** Minimum consecutive successful probes before a container is marked Ready. Updates deployment, resulting in respawn of dnssdist pods (default: 2)
- **readinessTimeoutSeconds:** Number of seconds after which the readiness probes time out. Updates deployment, resulting in respawn of dnssdist pods (default: 1)
- **replicas:** Default number of replicas in a dnssdist deployment (default: 2)
- **roundRobinFailOnNoServer:** By default the roundrobin load-balancing policy will still try to select a backend even if all backends are currently down. Setting this to true will make the policy fail and return that no server is available instead. (default: *false*)
- **servFailWhenNoServer:** If true, return a ServFail when no servers are available, instead of the default behaviour of dropping the query. (default: *false*)
- **serviceLabels:** Labels to be added to each Service object (default: *{}*)
- **stekLength:** Length of a single STEK ticket, in bytes (default: 80)
- **stekMaxAge:** Interval in seconds at which a new STEK ticket should be generated and the oldest one removed (default: 43200)
- **stekPollInterval:** Interval in seconds at which a check should be performed for an updated set of STEK tickets (default: 15)
- **stekCount:** Number of STEK tickets to keep stored. Recommended to keep this value at least at ≥ 2 (default: 5)
- **webserverACLAllowAll:** Allow all inbound traffic to dnssdist webserver, regardless of source IP (default: *true*)
- **webserverACL:** Netmasks to allow webserver traffic from (default: *127.0.0.1/32, 192.168.0.0/16, 10.0.0.0/8, 172.16.0.0/12, ::1, fc00::/7*)
- **webserverPassword:** Instead of generating a password for the webserver, set a static one (default: generated and stored in a secret)
- **weightedBalancingFactor:** Set the maximum imbalance between the number of outstanding queries intended for a given server, based on its weight, and the actual number, when using the weighted or wrandom load-balancing policy. Default is 0, which disables the bounded-load algorithm. (default: 0)
- **ecs:** (dnssdist ECS functions)

- **setECSSOverride**: Whether to override an existing EDNS Client Subnet option present in the query (only effective when the backend server has annotation useClientSubnet = true). (Dnsdist default)
- **setECSSourcePrefixV4**: Truncate the requestors IPv4 address to this length, in bits (only effective when the backend server has annotation useClientSubnet = true). (Dnsdist default)
- **setECSSourcePrefixV6**: Truncate the requestors IPv6 address to this length, in bits (only effective when the backend server has annotation useClientSubnet = true). (Dnsdist default)
- **hpa**: (Horizontal Pod Autoscaler defaults)
 - **enabled**: Enable or disable the HPA (default: *false*)
 - **minReplicas**: Minimum # of replicas (default: 2)
 - **maxReplicas**: Maximum # of replicas (default: 4)
 - **metrics**: Metric(s) upon which to make decisions regarding scaling. Must be an array of MetricSpec (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#metricspec-v2beta2-autoscaling>). Examples are in the helm values.
 - **behavior**: Behavior of the HPA, must be instance of HorizontalPodAutoscalerBehavior (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#horizontalpodautoscalerspec-v2beta2-autoscaling>).
- **ringBuffers**: (Ringbuffer configuration)
 - **retries**: Number of shards to attempt to lock without blocking before giving up and simply blocking while waiting for the next shard to be available. Defaults to 5 if there is more than 1 shard, else it defaults to 0. (Dnsdist default)
 - **shards**: Number of shards to use to limit lock contention, defaults to 1. (Dnsdist default)
 - **size**: Maximum amount of queries to keep in the ringbuffer, defaults to 10000. (Dnsdist default)
- **securityPolling**: (Security polling configuration)
 - **securityPollInterval**: Interval between security pollings, in seconds. Defaults to 3600. (Dnsdist default)
 - **securityPollSuffix**: Domain name from which to query security update notifications. Setting this to an empty string disables secpoll. (Dnsdist default)
- **tuning**: (dnsdist tuning functions)
 - **setCacheCleaningDelay**: Interval in seconds between two runs of the cache cleaning algorithm, removing expired entries. (Dnsdist default)
 - **setCacheCleaningPercentage**: Percentage of the cache that the cache cleaning algorithm will try to free by removing expired entries. By default (100), all expired entries are removed. (Dnsdist default)
 - **setMaxTCPClientThreads**: Maximum amount of TCP client threads, handling TCP connections. By default this value is 10, unless more than 10 TCP listen sockets have been defined. (Dnsdist default)

- **setMaxTCPConnectionDuration:** Maximum duration of an incoming TCP connection, in seconds. 0 (the default) means unlimited. (Dnsdist default)
- **setMaxTCPConnectionsPerClient:** Maximum number of TCP connections per client. 0 (the default) means unlimited. (Dnsdist default)
- **setMaxTCPQueriesPerConnection:** Maximum number of queries in an incoming TCP connection. 0 (the default) means unlimited. (Dnsdist default)
- **setMaxTCPQueuedConnections:** Maximum number of TCP connections queued (waiting to be picked up by a client thread), defaults to 1000. 0 means unlimited. (Dnsdist default)
- **setMaxUDPOutstanding:** Maximum number of outstanding UDP queries to a given backend server, defaults to 65535. (Dnsdist default)
- **setStaleCacheEntriesTTL:** TTL for expired cache entries to be eligible as answer when no backends are available for a query, in seconds. (Dnsdist default)
- **setTCPRecvTimeout:** Read timeout on TCP connections from the client, in seconds. (Dnsdist default)
- **setTCPSendTimeout:** Write timeout on TCP connections from the client, in seconds. (Dnsdist default)
- **setUDPTimeout:** Maximum time dnsdist will wait for a response from a backend over UDP, in seconds. Defaults to 2. (Dnsdist default)
- **agentResources:** (dnsdist agent resource allocation defaults)
 - **limits:** (Limit amounts)
 - * **cpu:** Limit amount of CPU (Kubernetes default)
 - * **memory:** Limit amount of memory (Kubernetes default)
 - **requests:** (Request amounts)
 - * **cpu:** Request amount of CPU (Kubernetes default)
 - * **memory:** Request amount of memory (Kubernetes default)
- **rpcServerResources:** (dnsdist RPC server resource allocation defaults)
 - **limits:** (Limit amounts)
 - * **cpu:** Limit amount of CPU (Kubernetes default)
 - * **memory:** Limit amount of memory (Kubernetes default)
 - **requests:** (Request amounts)
 - * **cpu:** Request amount of CPU (Kubernetes default)
 - * **memory:** Request amount of memory (Kubernetes default)
- **stateResources:** (dnsdist state resource allocation defaults)
 - **limits:** (Limit amounts)
 - * **cpu:** Limit amount of CPU (Kubernetes default)
 - * **memory:** Limit amount of memory (Kubernetes default)
 - **requests:** (Request amounts)

- * **cpu**: Request amount of CPU (Kubernetes default)
- * **memory**: Request amount of memory (Kubernetes default)
- **resources**: (dnsdist resource allocation defaults)
 - **limits**: (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests**: (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)

8.3 recursor

Default settings for all recursor instances, configurable under 'recursor' in helm values.

- **affinity**: Kubernetes pod affinity (default: *{}*)
- **antiAffinityPreset**: Pod anti affinity, if *affinity* is not set (default: *preferred*)
- **apiKey**: API key used to access the /api endpoint, used to configure a static key (default: generated and stored in a secret)
- **metricsPath**: Path on which Prometheus metrics will be served (default: */metrics*)
- **metricsPort**: Port on which Prometheus metrics will be served (default: *8082*)
- **nodeSelector**: Kubernetes pod nodeSelector (default: *{}*)
- **podAnnotations**: Annotations to be added to each Pod
- **podLabels**: Labels to be added to each Pod
- **podSecurityContext**: Kubernetes Pod security context (default: *953* as fsGroup, runAsUser & runAsGroup)
- **readinessFailureThreshold**: When a probe fails, Kubernetes will try this many times before marking the container as Unready. Updates deployment, resulting in respawn of recursor pods (default: *2*)
- **readinessInitialDelaySeconds**: Number of seconds after the containers have started before readiness probes are initiated. Updates deployment, resulting in respawn of recursor pods. (default: *5*)
- **readinessPeriodSeconds**: How often (in seconds) to perform the readiness probes. Updates deployment, resulting in respawn of recursor pods (default: *2*)
- **readinessStateProbeInterval**: How often (in seconds) the agent will judge the health state of the recursor agent. (default: *2*)
- **readinessSuccessThreshold**: Minimum consecutive successful probes before a container is marked Ready. Updates deployment, resulting in respawn of recursor pods (default: *2*)
- **readinessTimeoutSeconds**: Number of seconds after which the readiness probes time out. Updates deployment, resulting in respawn of recursor pods (default: *1*)

- **replicas**: Default number of replicas in a recursor deployment (default: 2)
- **serviceLabels**: Labels to be added to each Service object (default: {})
- **webserverACLAllowAll**: Allow all inbound traffic to recursor webserver, regardless of source IP (default: *true*)
- **webserverACL**: Netmasks to allow webserver traffic from (default: *127.0.0.1/32, 192.168.0.0/16, 10.0.0.0/8, 172.16.0.0/12, ::1, fc00::/7*)
- **webserverPassword**: Instead of generating a password for the webserver, set a static one (default: generated and stored in a secret)
- **hpa**: (Horizontal Pod Autoscaler defaults)
 - **enabled**: Enable or disable the HPA (default: *false*)
 - **minReplicas**: Minimum # of replicas (default: 2)
 - **maxReplicas**: Maximum # of replicas (default: 4)
 - **metrics**: Metric(s) upon which to make decisions regarding scaling. Must be an array of MetricSpec (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#metricspec-v2beta2-autoscaling>). Examples are in the helm values.
 - **behavior**: Behavior of the HPA, must be instance of HorizontalPodAutoscalerBehavior (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#horizontalpodautoscalerspec-v2beta2-autoscaling>).
- **agentResources**: (recursor agent resource allocation defaults)
 - **limits**: (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests**: (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)
- **resources**: (recursor resource allocation defaults)
 - **limits**: (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests**: (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)

8.4 resolver

Default settings for resolver instances, configurable under 'resolver' in helm values.

- **backendDefaultPort:** Port on which the endpoints belonging to a resolver partition will receive traffic (default: 53)
- **serviceLabels:** Labels to be added to each Service object (default: `{}`)
- **servicePort:** Port on which a resolver service will listen (unused in normal operation, as the service is only used to discover the corresponding endpoints). (default: 53)

8.5 zoneControl

Default settings for all ZoneControl instances, configurable under 'zonecontrol' in helm values.

- **affinity:** Kubernetes pod affinity (default: `{}`)
- **antiAffinityPreset:** Pod anti affinity, if *affinity* is not set (default: *preferred*)
- **nodeSelector:** Kubernetes pod nodeSelector (default: `{}`)
- **podAnnotations:** Annotations to be added to each Pod
- **podLabels:** Labels to be added to each Pod
- **podSecurityContext:** Kubernetes Pod security context (default: 953 as fsGroup, runAsUser & runAsGroup)
- **replicas:** Default number of replicas in a recursor deployment (default: 2)
- **serviceLabels:** Labels to be added to each Service object (default: `{}`)
- **syncJobTTL:** Keep finished synchronisation jobs for this amount of seconds before allowing Kubernetes to remove them (default: 86400)
- **operator:** (Synchronisation operator defaults)
 - **podAnnotations:** Annotations to be added to each Pod
 - **podLabels:** Labels to be added to each Pod
- **resources:** (auth resource allocation defaults)
 - **limits:** (Limit amounts)
 - * **cpu:** Limit amount of CPU (Kubernetes default)
 - * **memory:** Limit amount of memory (Kubernetes default)
 - **requests:** (Request amounts)
 - * **cpu:** Request amount of CPU (Kubernetes default)
 - * **memory:** Request amount of memory (Kubernetes default)

9 Instances

9.1 auths

Configuration of auth instances

Key: name (Name of the auth instance)

9.1.1 Parameters

- **affinity:** Kubernetes pod affinity
- **antiAffinityPreset:** Pod anti affinity preset (Accepted values: *preferred* or *required*)
- **hostNetwork:** Use host networking for auth pods
- **nodeSelector:** Kubernetes pod nodeSelector
- **podAnnotations:** Annotations to be added to each Pod
- **podLabels:** Labels to be added to each Pod
- **podSecurityContext:** Kubernetes Pod security context (default: 953 as fsGroup, runAsUser & runAsGroup)
- **replicas:** Default number of replicas in a auth deployment (default: 2)
- **revisionHistoryLimit:** Default 'revisionHistoryLimit' for auth deployments (default: 0)

9.1.2 Parameter Sets

- **api** (Configuration of access to the auth API endpoint)
 - **ingress:** Ingress object to expose the auth API endpoint via an ingress managed by an ingress controller (For formatting example, see the *Exposing auth API* chapter)
 - **service:** Service object to expose the auth API endpoint (For formatting example, see the *Exposing dnsdist* chapter, which covers the *service* format to add ClusterIP, NodePort or LoadBalancer services)
- **dnsdist** (Settings to be applied to each auth instance when added to dnsdist as a server)
 - **addXPF:** Add the client's IP address and port to the query, along with the original destination address and port. Default is disabled (0)
 - **checkClass:** Number to use as QCLASS in the health-check query, default is DNSClass.IN

- **checkInterval:** The time in seconds between health checks
- **checkName:** String to use as QNAME in the health-check query, default is "a.root-servers.net."
- **checkTimeout:** The timeout (in milliseconds) of a health-check query, default to 1000 (1s)
- **checkType:** String to use as QTYPE in the health-check query, default is "A"
- **disableZeroScope:** Disable the EDNS Client Subnet 'zero scope' feature, which does a cache lookup for an answer valid for all subnets (ECS scope of 0) before adding ECS information to the query and doing the regular lookup. This requires the *parseECS* option of the corresponding cache to be set to true
- **maxCheckFailures:** Allow this amount of check failures before declaring the backend down, default is 1
- **mustResolve:** Set to true when the health check MUST return a RCODE different from NXDomain, ServFail and Refused. Default is false, meaning that every RCODE except ServFail is considered valid
- **order:** The order of servers in this set, used by the *leastOutstanding* and *firstAvailable* policies
- **qps:** Limit the number of queries per second to this amount, when using the *firstAvailable* policy
- **reconnectOnUp:** Close and reopen the sockets when a server transits from Down to Up. This helps when an interface is missing when dnssdist is started. Default is false
- **retries:** The number of TCP connection attempts to servers in this set, for a given query
- **rise:** Require NUM consecutive successful checks before declaring the backend up, default is 1
- **setCD:** Set the CD (Checking Disabled) flag in the health-check query, default is false
- **sockets:** Number of sockets (and thus source ports) used toward the backend server, defaults to 1
- **source:** Name of the interface which Dnsdist will use to try to send traffic to this Recursor
- **tcpConnectTimeout:** The timeout (in seconds) of a TCP connection attempt
- **tcpFastOpen:** Whether to enable TCP Fast Open
- **tcpRecvTimeout:** The timeout (in seconds) of a TCP read attempt
- **tcpSendTimeout:** The timeout (in seconds) of a TCP write attempt
- **useClientSubnet:** Add the client's IP address in the EDNS Client Subnet option when forwarding the query to this backend
- **useProxyProtocol:** Add a proxy protocol header to the query, passing along the client's IP address and port along with the original destination address and port. Default is false

- **weight:** The weight of servers in this set, used by the *wrandom*, *whashed* and *chashed* policies, default is 1
- **config** (Auth configuration, any configuration item listed in the auth documentation (<https://doc.powerdns.com/authoritative/settings.html>) can be referenced here. Settings which are explicitly ignored due to conflicts with Cloud Control are filtered by 'web-server*', 'local*', 'disable-syslog', 'daemon', 'chroot', 'socket*', 'config*', 'primary', 'secondary' and 'autosecondary')
- **hpa** (Horizontal Pod Autoscaler - see helm values 'auth.hpa' for examples)
 - **enabled:** Enable or disable the HPA (default: *false*)
 - **minReplicas:** Minimum # of replicas (default: 2)
 - **maxReplicas:** Maximum # of replicas (default: 4)
 - **metrics:** Metric(s) upon which to make decisions regarding scaling. Must be an array of MetricSpec (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#metricspec-v2beta2-autoscaling>). Examples are in the helm values.
 - **behavior:** Behavior of the HPA, must be instance of HorizontalPodAutoscalerBehavior (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#horizontalpodautoscalerspec-v2beta2-autoscaling>).
- **postgres** (Settings to be applied to each postgres cluster/database when an auth deployment requests a postgres operator-managed database)
 - **parameters.max_connections:** Max connections parameter (default: 128)
 - **storage.size:** Size of the volume to request for each Postgres pod (default: 5Gi)
 - **storage.storageClassName:** Name of the Storage Class for the volumes in which Postgres data will be stored (default: unset, which means the Kubernetes cluster's default storage class)
 - **resources.limits.cpu:** Limit amount of CPU (default: 250m)
 - **resources.limits.memory:** Limit amount of memory (default: 256Mi)
 - **resources.requests.cpu:** Request amount of CPU (default: 500m)
 - **resources.requests.memory:** Request amount of memory (default: 512m)
 - **nodeAffinity:** Kubernetes node affinity (Note: Only configures the subset *nodeAffinity* of the parent *affinity*. See <https://kubernetes.io/docs/concepts/scheduling-eviction/assign-pod-node/#node-affinity>)
- **resources** (auth resource allocation defaults)
 - **limits** (Limit amounts)
 - * **cpu:** Limit amount of CPU (Kubernetes default)
 - * **memory:** Limit amount of memory (Kubernetes default)
 - **requests** (Request amounts)
 - * **cpu:** Request amount of CPU (Kubernetes default)
 - * **memory:** Request amount of memory (Kubernetes default)

9.1.3 Backends

When deploying Auth as part of CloudControl there are several backends you can choose (and combine, multiple backends is supported):

- **GeoIP:** This backend allows visitors to be sent to a server closer to them, with no appreciable delay, as would otherwise be incurred with a protocol level redirect.
- **LightningStream:** This backend allows synchronisation of multiple instances via an s3 bucket. This can be done within a single datacenter or spread over multiple datacenters.
- **MySQL:** This backend allows storing zones in a MySQL database.
- **Postgres:** This backend allows storing zones in a Postgres database, either pre-existing on your cluster or created at runtime using a Postgres Operator.

9.1.3.1 Postgres (pre-existing)

If you have an existing Postgres database available, you can configure a backend to utilize it. Configuring a pre-existing Postgres database can be done via the following configuration:

Format:

```
backends:  
- type: postgres  
  host: host-of-postgres-cluster  
  dbname: auth  
  user: some_user  
  password: some_user_password
```

Available parameters:

- type - Must be set to *postgres*
- host - Host of the Postgres cluster/service
- port - Port over which to access the Postgres database (Optional, default: 5432)
- dbname - Name of the database
- user - User with which to connect
- password - Password for *user*
- sslmode - Postgres *sslmode* to use while connecting (Optional, omitted if no value is provided)
- dnssec - Whether or not to enable DNSSEC processing for this backend (Optional, default: *false*)

Note: Cloud Control will manage the schema in the Postgres database. Before an Auth container starts, an init container checks the schema and creates/updates it if necessary.

9.1.3.2 Postgres (Operator-managed)

If you have deployed the postgres-operator chart to your Kubernetes cluster, you can configure a backend to use a operator-managed Postgres database. Configuring such a Postgres database can be done via the following configuration:

Format:

```
backends:  
- type: postgres  
  operator: true
```

Available parameters:

- type - Must be set to *postgres*
- operator - Must be set to *true*

The Postgres database which is created utilizes the default values which are exposed via the helm values in *auth.postgres*.

9.1.3.3 MySQL

If you have an existing MySQL database available, you can configure a backend to utilize it. Configuring a pre-existing MySQL database can be done via the following configuration:

Format:

```
backends:  
- type: mysql  
  host: host-of-mysql-cluster  
  dbname: auth  
  user: some_user  
  password: some_user_password
```

Available parameters:

- type - Must be set to *mysql*
- host - Host/IP of the MySQL cluster/service
- port - Port over which to access the MySQL database (Optional, default: 3306)
- dbname - Name of the database
- user - User with which to connect
- password - Password for *user*
- ssl - Can be set to *yes* to force connecting via SSL (Optional, default behaviour is to use SSL if the server announces this capability)
- group - Group to connect as (Optional, default: *client*)
- dnssec - Whether or not to enable DNSSEC processing for this backend (Optional, default: *no*)
- innodbReadCommitted - Use the InnoDB READ-COMMITTED transaction isolation level (Optional, default: *yes*)

- `timeout` - Timeout in seconds for each attempt to read from, or write to the server. A value of 0 will disable the timeout (Optional, default: 10)

Note: Cloud Control will manage the schema in the MySQL database. Before an Auth container starts, an init container checks the schema and creates/updates it if necessary.

9.1.3.4 GeolP

Configuring a GeolP backend requires configuring the following options:

Format:

```
backends:  
- type: geolp  
  databases: <Configuration of one or more GeoIP databases>  
  domains: <Configuration of domains>
```

Configuring *domains*: Please refer to the PowerDNS Authoritative Server documentation at <https://doc.powerdns.com/authoritative/backends/geolp.html#keys-explained>

Configuring *databases*:

The databases used by the GeolP backend are MMDB files, which allows you to use databases from several sources:

- MaxMind – A provider of GeoIP databases
- Custom - A database built by the Auth init container based on data you provide in the Helm configuration values

9.1.3.5 GeolP - MaxMind Database

Configuring a GeolP backend using a MaxMind database can be done via 2 methods:

- HTTP - Download the database using HTTP
- OCI - Download the database from an OCI-enabled registry, using the ORAS Client

9.1.3.6 GeolP - MaxMind Database - HTTP

Format:

```
databases:  
- name: MyDatabase  
  type: http  
  url: https://my_host/folder/my-database.mmdb  
  insecure: false  
  headers:  
    <List of additional headers to be passed>  
  params:  
    <List of additional parameters to be passed, these must be valid Curl parameters>
```

Explanation of each parameter:

- `name` - Required, must be unique for this backend
- `type` - Required, must be *http* to force a MaxMind HTTP download

- url - Required, full address of the database to be downloaded
- insecure - Optional, set to *true* if you need to download the database from an HTTPS URL without valid certificates
- headers - Dict of *key: value* pairs, where *key* is the header name and *value* is the value of the header
- params - Dict of *key: value* pairs, where *key* is the name of the Curl parameter and *value* is the value of the parameter

Minimal required configuration for downloading a MaxMind database using HTTP(S):

```
databases:
- name: MyDatabase
  type: http
  url: https://some_host/my-database.mmdb
```

Example using headers & params:

```
databases:
- name: MyDatabase
  type: http
  url: https://some_host/my-database.mmdb
  headers:
    Authorization: Basic bXl1sfdc2Vy0m15cGFzetbcvbc3sdfdvcmQ=
  params:
    proxy: "http://my_user:my_password@some_proxy:8080"
```

Above example will send a Basic auth header & attempt to connect via the proxy *some_proxy:8080*

9.1.3.7 GeoIP - MaxMind Database - OCI

Format:

```
databases:
- name: MyOCIDB
  type: oci
  artifact: my_registry/repository/geo-city-mmdb:v2.4.0
  user: MyUser
  token: MyPassword
```

Explanation of each parameter:

- name - Required, must be unique for this backend
- type - Required, must be *oci* to force a MaxMind OCI download
- artifact - Required, full address of the database to be downloaded
- user - Required, User with which to connect to the registry
- token - Required, Token/Password for *user*

9.1.3.8 GeolP - Custom Database

Configuring a GeolP backend using a custom database can be done via the following configuration:

```
databases:  
- name: localdb  
  type: generate  
  datacenters:  
    <List of datacenters - see below>
```

Explanation of each parameter:

- name - Required, must be unique for this backend
- type - Required, must be *generate* to force a custom database to be generated
- datacenters - Required, must be populated according to the below format

Example datacenter configuration:

```
- name: Amsterdam  
  networks:  
    - 10.0.1.0/24  
    - 10.0.2.0/24  
    - 10.0.3.0/24  
    - 10.0.4.0/24  
    - 10.0.5.0/24  
    - 10.0.6.0/24  
  lat: 52.370216  
  long: 4.895168
```

Explanation of each parameter:

- name - Required, must be unique for this datacenter
- networks - Required, list of networks to be assigned to this datacenter
- lat - Required, longitude of this datacenter
- long - Required, latitude of this datacenter

The latitude & longitude are used to calculate distances between datacenters, which is how the GeolP backend determines the closest available recipient of traffic. There are many tools available online to obtain the latitude & longitude of locations.

The following example simulates a setup where we have 2 datacenters, in Amsterdam & Rotterdam:

```
databases:  
- name: localdb  
  type: generate  
  datacenters:  
    - name: Amsterdam  
      networks:  
        - 10.0.1.0/24  
        - 10.0.2.0/24  
        - 10.0.3.0/24  
        - 10.0.4.0/24
```

(continues on next page)

(continued from previous page)

```

- 10.0.5.0/24
- 10.0.6.0/24
lat: 52.370216
long: 4.895168
- name: Rotterdam
networks:
- 10.1.1.0/24
- 10.1.2.0/24
- 10.1.3.0/24
- 10.1.4.0/24
- 10.1.5.0/24
- 10.1.6.0/24
lat: 51.924419
long: 4.477733

```

9.1.3.9 LightningStream

Configuration of a LightningStream backend primarily requires supplying the details required to connect to a shared s3 bucket.

Notes:

- Account used to access the s3 bucket must have privileges to read, write & list
- All auth instances that have the same s3 bucket configured will contain the same zones & records. You cannot share the same s3 bucket amongst auth instances which you intend to have different data.
- Access and Secret keys must be limited to characters from the Base64 alphabet (defined in RFC 4648). Usage of characters outside this alphabet can lead to inability to connect to the s3 bucket.

The format to configure a LightningStream backend:

```

backends:
- type: ls
  access_key: MY_ACCESS_KEY
  secret_key: MY_SECRET_KEY
  bucket: mybucket
  endpoint: https://my.s3.endpoint

```

Required parameters:

- type - Required, must be *ls* to force a LightningStream backend
- access_key - Required, access key to authenticate with the endpoint
- secret_key - Required, secret key to authenticate with the endpoint
- bucket - Required, name of the s3 bucket
- endpoint - Required, URL to access the s3 service

Optional parameters:

- cleanupDisabled - Set to *true* to disable the cleanup mechanism (Default: *false*)
- cleanupInterval - Interval between cleanup runs (Default: *5m*)

- `cleanupMustKeepInterval` - Determines how long snapshots must be kept after they appear in the bucket, even if a newer snapshot is available. Defaults to *10m*
- `cleanupRemoveOldInstancesInterval` - Determines when an instance is considered stale and the latest snapshot for the instance can be considered for removal. Defaults to *168h* (7 days)
- `health` - Allows for configuration of the error and warning thresholds used to determine readiness of LightningStream via *unreadyIfError*, *unreadyIfWarning* and *waitForInitialSync* (see *health configuration* section below)
- `loglevel` - Defaults to *info*. Available options: *debug*, *info*, *warning*, *error*, *fatal*
- `lmdbEmptyDir` - Configuration of the *EmptyDir* volume used to store LMDB. Defaults to: *medium: "Memory"*
- `lmdbPollInterval` - Minimum time between checking for new LMDB transactions. Defaults to *1s*
- `lmdbLogStatsInterval` - Interval for logging LMDB stats. Defaults to *30m*
- `mapSize` - Size (in megabytes) of the LMDB databases. Defaults to *1000* and can be increased for large datasets
- `migratorInterval` - Time between checks performed by the migrator to see if a migration is required. Defaults to *5s*
- `region` - Set this to the region associated with your s3 bucket, if your s3 service requires this
- `removeOldSchemaAge` - Time since the last successful migration of an old schema before removing it, if no updates have been made to the schema since then. Defaults to *672h`*
- `removeOldSchemaEnabled`: Whether or not the migrator should clean up old schemas if they have been migrated successfully and not seen any updates since. Defaults to *true*
- `storagePollInterval` - Minimum time between polling the storage backend for new snapshots. Defaults to *1s*
- `storageRetryInterval` - Interval to retry a storage operation after failure. Defaults to *5s*
- `storageRetryCount` - Number of times to retry a storage operation after failure, before giving up. Defaults to *9999999*
- `tls` - Allows for configuration of a trusted CA and/or disable certificate validation (see *TLS Configuration* section below)
- `unreadyIfError` - Set readiness of LightningStream container to *NotReady* if LightningStream healthz endpoint reports any errors (Default: *true*)
- `unreadyIfWarning` - Set readiness of LightningStream container to *NotReady* if LightningStream healthz endpoint reports any warnings (Default: *false*)
- `waitForInitialSync` - Keep readiness of LightningStream container at *NotReady* until LightningStream has successfully finished the initial sync between the Auth container and the s3 bucket (Default: *true*)

snapshots in the S3 buckets

- start: Thresholds for reporting errors/warnings regarding the initial sync performed when LightningStream starts

Each section has the same 3 options:

- warn_duration: Duration after which a failing operation will report as being in *warning* state
- error_duration: Duration after which a failing operation will report as being in *error* state
- interval: Interval between evaluation of the state of the operation

For example, a configuration as follows for *load*:

```
storage_load:
  warn_duration: 30s
  error_duration: 2m
  interval: 1s
```

Would lead to the following health monitoring:

```
Every 1 second
If this operation has failed for more than 2 minutes, report error
Else
  If this operation has failed for more than 30 seconds, report warning
  Else do not report any warnings/errors for this operation
```

Overriding these defaults can be done as follows:

```
backends:
- type: ls
  access_key: MY_ACCESS_KEY
  secret_key: MY_SECRET_KEY
  bucket: mybucket
  endpoint: https://my.s3.endpoint
  health:
    storage_load:
      warn_duration: 2m
      error_duration: 5m
      interval: 5s
```

9.2 dnssdists

Configuration of dnssdist instances

Key: name (Name of the dnssdist instance)

9.2.1 Parameters

- **aclAdd**: Netmasks allowed to access dnsmdist, in addition to the loopback, RFC1918 and other local addresses. Overrides a AllowAll setting (if configured) on the global dnsmdist defaults.
- **aclAllowAll**: Allow all inbound traffic to dnsmdist, regardless of source IP.
- **affinity**: Kubernetes pod affinity
- **antiAffinityPreset**: Pod anti affinity preset (Accepted values: *preferred* or *required*)
- **do53Locals**: Default amount of Do53 listen sockets per dnsmdist pod (default: 1)
- **do53TcpFastOpenQueueSize**: Default size of the TCP Fast Open queue on Do53 listen sockets (Dnsmdist default)
- **do53TcpListenQueueSize**: Default size of the listen queue on Do53 listen sockets (Dnsmdist default)
- **hostNetwork**: Use host networking for dnsmdist pods
- **luaScript**: Lua script to be included in each dnsmdist pod (See 'Overview' document for usage examples)
- **nodeSelector**: Kubernetes pod nodeSelector
- **podAnnotations**: Annotations to be added to each Pod
- **podLabels**: Labels to be added to each Pod
- **podSecurityContext**: Kubernetes Pod security context (default: 953 as fsGroup, runAsUser & runAsGroup)
- **replicas**: Default number of replicas in a dnsmdist deployment (default: 2)
- **revisionHistoryLimit**: Default 'revisionHistoryLimit' for dnsmdist deployments (default: 0)
- **verbose**: Be verbose (default: *false*)

9.2.2 Parameter Sets

- **config** (Dnsmdist Configuration)
 - **addEDNSToSelfGeneratedResponses**: Whether to add EDNS to self-generated responses, provided that the initial query had EDNS. (Dnsmdist default)
 - **allowEmptyResponse**: Set to true (defaults to false) to allow empty responses (qdcount=0) with a NoError or NXDomain rcode (default) from backends. dnsmdist drops these responses by default because it can't match them against the initial query since they don't contain the qname, qtype and qclass, and therefore the risk of collision is much higher than with regular responses. (Dnsmdist default)
 - **consistentHashingBalancingFactor**: Maximum imbalance between the number of outstanding queries intended for a given server, based on its weight, and the actual number, when using the hashed consistent hashing load-balancing policy. Default is 0, which disables the bounded-load algorithm. (Dnsmdist default)

- **payloadSizeOnSelfGeneratedAnswers:** Set the UDP payload size advertised via EDNS on self-generated responses. In accordance with RFC 6891, values lower than 512 will be treated as equal to 512. (Dnsdist default)
- **roundRobinFailOnNoServer:** By default the roundrobin load-balancing policy will still try to select a backend even if all backends are currently down. Setting this to true will make the policy fail and return that no server is available instead. (Dnsdist default)
- **servFailWhenNoServer:** If set, return a ServFail when no servers are available, instead of the default behaviour of dropping the query. (Dnsdist default)
- **verboseHealthChecks:** Set whether health check errors should be logged. This is turned off by default. (Dnsdist default)
- **weightedBalancingFactor:** Maximum imbalance between the number of outstanding queries intended for a given server, based on its weight, and the actual number, when using the whashed or wrandom load-balancing policy. Default is 0, which disables the bounded-load algorithm. (Dnsdist default)
- **ecs** (dnsdist ECS functions)
 - **setECSSetOverride:** Whether to override an existing EDNS Client Subnet option present in the query (only effective when the backend server has annotation useClientSubnet = true). (Dnsdist default)
 - **setECSSourcePrefixV4:** Truncate the requestors IPv4 address to this length, in bits (only effective when the backend server has annotation useClientSubnet = true). (Dnsdist default)
 - **setECSSourcePrefixV6:** Truncate the requestors IPv6 address to this length, in bits (only effective when the backend server has annotation useClientSubnet = true). (Dnsdist default)
- **hpa** (Horizontal Pod Autoscaler - see helm values 'dnsdist.hpa' for examples)
 - **enabled:** Enable or disable the HPA (default: *false*)
 - **minReplicas:** Minimum # of replicas (default: 2)
 - **maxReplicas:** Maximum # of replicas (default: 4)
 - **metrics:** Metric(s) upon which to make decisions regarding scaling. Must be an array of MetricSpec (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#metricspec-v2beta2-autoscaling>). Examples are in the helm values.
 - **behavior:** Behavior of the HPA, must be instance of HorizontalPodAutoscalerBehavior (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#horizontalpodautoscalerspec-v2beta2-autoscaling>).
- **readiness** (Readiness probe Configuration)
 - **bindInterface:** Name of interface to which the readiness probe will bind
 - **disabled:** Whether or not to instruct Kubernetes to poll the agent for readiness state. (default: *false*)
 - **do53ProbeInterval:** How often (in seconds) the agent will judge the health state of dnsdist via tests against the Do53 listeners. (default: 2)

- **do53QDomain**: Domain used in the query to judge whether the Do53 listeners of a dnsmdist container are healthy and ready for traffic. (default: *a.root-servers.net*)
- **do53QTimeout**: Number of seconds after which the query used to judge whether the Do53 listeners of a dnsmdist container are healthy and ready for traffic time out. (default: *1*)
- **do53QType**: Type of query used to judge whether the Do53 listeners of a dnsmdist container are healthy and ready for traffic. (default: *A*)
- **failureThreshold**: When a probe fails, Kubernetes will try this many times before marking the container as Unready. Updates deployment, resulting in respawn of dnsmdist pods (default: *2*)
- **initialDelaySeconds**: Number of seconds after the containers have started before readiness probes are initiated. Updates deployment, resulting in respawn of dnsmdist pods. (default: *5*)
- **periodSeconds**: How often (in seconds) to perform the readiness probes. Updates deployment, resulting in respawn of dnsmdist pods (default: *2*)
- **stateProbeInterval**: How often (in seconds) the agent will judge the health state of the dnsmdist agent. (default: *2*)
- **successThreshold**: Minimum consecutive successful probes before a container is marked Ready. Updates deployment, resulting in respawn of dnsmdist pods (default: *2*)
- **timeoutSeconds**: Number of seconds after which the readiness probes time out. Updates deployment, resulting in respawn of dnsmdist pods (default: *1*)
- **recursor** (Enable & configure recursor containers co-hosted within the dnsmdist pod)
 - **backendsPerServer**: Amount of server objects to create in dnsmdist for each recursor container (default: *1*)
 - **pool**: Name of the pool to which the co-hosted recursors should be added (default: *default*)
 - **replicas**: Number of recursor containers which should be added to each dnsmdist pod. This must be set to ≥ 1 for any recursors to be added (default: *0*)
 - All options listed under the *Configuration of recursor instances* chapter can also be added here, except for: *affinity*, *antiAffinity*, *hostNetwork*, *nodeSelector* & *revisionHistoryLimit* (as those are pod-specific and those are controlled by dnsmdist for this pod)
- **resources** (dnsmdist resource allocation defaults)
 - **limits** (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests** (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)
- **ringBuffers** (Ringbuffer configuration)

- **retries**: Number of shards to attempt to lock without blocking before giving up and simply blocking while waiting for the next shard to be available. Defaults to 5 if there is more than 1 shard, else it defaults to 0. (Dnsdist default)
- **shards**: Number of shards to use to limit lock contention, defaults to 1. (Dnsdist default)
- **size**: Maximum amount of queries to keep in the ringbuffer, defaults to 10000. (Dnsdist default)
- **securityPolling** (Security polling configuration)
 - **securityPollInterval**: Interval between security pollings, in seconds. Defaults to 3600. (Dnsdist default)
 - **securityPollSuffix**: Domain name from which to query security update notifications. Setting this to an empty string disables secpoll. (Dnsdist default)
- **service** (Configuration of the Kubernetes service object **Note**: See the section 'Exposing dnsdist' for more details and examples on how to configure this)
 - **sharedService**: Whether or not to create a single service with multiple ports (ie: UDP & TCP). Default: *true*
 - **servicePerPort**: Whether or not to create a service for each port (ie: a service for UDP & a service for TCP). Default: *false*
 - **type**: Type of service (One of NodePort, ClusterIP, LoadBalancer). Defaults to ClusterIP
 - **annotations**: List of annotations to add to the Service
 - **loadBalancerIP**: For a Service of type LoadBalancer, a loadbalancer IP can be requested here. If left empty/undefined, this will be assigned by your LoadBalancer provider
 - **ports**: A dictionary of ports you want to have exposed via the Service
- **tuning** (dnsdist tuning functions)
 - **setCacheCleaningDelay**: Interval in seconds between two runs of the cache cleaning algorithm, removing expired entries. (Dnsdist default)
 - **setCacheCleaningPercentage**: Percentage of the cache that the cache cleaning algorithm will try to free by removing expired entries. By default (100), all expired entries are removed. (Dnsdist default)
 - **setMaxTCPClientThreads**: Maximum amount of TCP client threads, handling TCP connections. By default this value is 10, unless more than 10 TCP listen sockets have been defined. (Dnsdist default)
 - **setMaxTCPConnectionDuration**: Maximum duration of an incoming TCP connection, in seconds. 0 (the default) means unlimited. (Dnsdist default)
 - **setMaxTCPConnectionsPerClient**: Maximum number of TCP connections per client. 0 (the default) means unlimited. (Dnsdist default)
 - **setMaxTCPQueriesPerConnection**: Maximum number of queries in an incoming TCP connection. 0 (the default) means unlimited. (Dnsdist default)

- **setMaxTCPQueuedConnections:** Maximum number of TCP connections queued (waiting to be picked up by a client thread), defaults to 1000. 0 means unlimited. (Dnsdist default)
- **setMaxUDPOutstanding:** Maximum number of outstanding UDP queries to a given backend server, defaults to 65535. (Dnsdist default)
- **setStaleCacheEntriesTTL:** TTL for expired cache entries to be eligible as answer when no backends are available for a query, in seconds. (Dnsdist default)
- **setTCPRecvTimeout:** Read timeout on TCP connections from the client, in seconds. (Dnsdist default)
- **setTCPSendTimeout:** Write timeout on TCP connections from the client, in seconds. (Dnsdist default)
- **setUDPTimeout:** Maximum time dnsdist will wait for a response from a backend over UDP, in seconds. Defaults to 2. (Dnsdist default)

9.2.3 Server Pools

pools (Configuration of pools)

Key: name (Name of the pool)

- **ecs:** Set to true if dnsdist should add EDNS Client Subnet information to the query before looking up into the cache, when all servers from this pool are down. If at least one server is up, the preference of the selected server is used, this parameter is only useful if all the backends in this pool are down and have EDNS Client Subnet enabled, since the queries in the cache will have been inserted with ECS information. Default is false. (Dnsdist default)
- **serverGroups:** List of [Name] of recursor & resolver instances whose endpoints will be member of this pool (Dnsdist default)
- **serverPolicy:** Policy for dnsdist to use to select the server in this pool to send a query to. Supported policies are 'leastOutstanding', 'firstAvailable', 'wrandom', 'whashed', 'chashed' & 'roundrobin' (Dnsdist default)
- **packetcache** (Configurable cache that holds responses from prior requests served by the pool)
 - **cookieHashing:** Whether EDNS Cookie values will be hashed, resulting in separate entries for different cookies in the packet cache. This is required if the backend is sending answers with EDNS Cookies, otherwise a client might receive an answer with the wrong cookie. (Dnsdist default)
 - **deferrableInsertLock:** Whether the cache should give up insertion if the lock is held by another thread, or simply wait to get the lock. (Dnsdist default)
 - **keepStaleData:** Whether to suspend the removal of expired entries from the cache when there is no backend available in at least one of the pools using this cache. (Dnsdist default)
 - **maxEntries:** Max (Dnsdist default)
 - **maxNegativeTTL:** Cache a NXDomain or NoData answer from the backend for at most this amount of seconds, even if the TTL of the SOA record is higher. (Dnsdist default)

- **maxTTL**: Cap the TTL for records to this number. (Dnsdist default)
- **minTTL**: Do not cache entries with a TTL lower than this. (Dnsdist default)
- **numberOfShards**: Number of shards to divide the cache into, to reduce lock contention. (Dnsdist default)
- **parseECS**: Whether any EDNS Client Subnet option present in the query should be extracted and stored to be able to detect hash collisions involving queries with the same qname, qtype and qclass but a different incoming ECS value. (Dnsdist default)
- **staleTTL**: When the backend servers are not reachable, and global configuration set-StaleCacheEntriesTTL is set appropriately, TTL that will be used when a stale cache entry is returned. (Dnsdist default)
- **temporaryFailureTTL**: On a SERVFAIL or REFUSED from the backend, cache for this amount of seconds. (Dnsdist default)

9.2.4 DNS over HTTP(S)

doh (List of configurations of DoH listeners)

- **name**: Name of the DoH listener (used for naming the corresponding Service objects, etc)
- **locals**: Amount of listen sockets per dnsdist pod (default: 1)
- **headers**: Dictionary of HeaderName:HeaderValue pairs to add to each response (Omitted on redirect responses)
- **secrets**: List of names of Secrets (Type: kubernetes.io/tls) containing certificates & keys to be used on the DoH listener. Key must be in *tls.key* node and certificate (+ intermediates if applicable) must be in *tls.crt* node.
- **service**: Configuration of the Kubernetes service object (Note: See the section 'Exposing dnsdist' for more details and examples on how to configure this)
- **stekSecret**: Name of a Secret (Type: Opaque) with stek tickets included in the *tickets* node. This secret is monitored for changes and will be updated in dnsdist whenever a change is detected. Default: CloudControl will generate and update tickets as per the defaults (See parameters named stek* in the dnsdist defaults section)
- **urls**: List of URLs to respond to (Default: /dns-query)
- **config** (Configuration options for the DoH listener)
 - **ciphers**: The TLS ciphers to use, in OpenSSL format. Ciphers for TLS 1.3 must be specified via ciphersTLS13.
 - **ciphersTLS13**: The TLS ciphers to use for TLS 1.3, in OpenSSL format.
 - **enableRenegotiation**: Whether secure TLS renegotiation should be enabled. Default: false (Disabled by default since it increases the attack surface and is seldom used for DNS)
 - **exactPathMatching**: Whether to do exact path matching of the query path against the paths configured in urls (true) or to accept sub-paths (false). Default: true
 - **idleTimeout**: Set the idle timeout, in seconds. (Default: 30)

- **internalPipeBufferSize:** Set the size in bytes of the internal buffer of the pipes used internally to pass queries and responses between threads. Default: 1048576
- **maxConcurrentTCPConnections:** Maximum number of concurrent incoming TCP connections. Default: 0 (which means unlimited).
- **minTLSVersion:** Minimum version of the TLS protocol to support. Possible values are *tls1.0*, *tls1.1*, *tls1.2* and *tls1.3*. Default is to require at least TLS 1.0.
- **numberOfStoredSessions:** The maximum number of sessions kept in memory at the same time. Default is 20480. Setting this value to 0 disables stored session entirely.
- **preferServerCiphers:** Whether to prefer the order of ciphers set by the server instead of the one set by the client. Default is true, meaning that the order of the server is used.
- **releaseBuffers:** Whether OpenSSL should release its I/O buffers when a connection goes idle, saving roughly 35 kB of memory per connection. Default: true
- **sendCacheControlHeaders:** Whether to parse the response to find the lowest TTL and set a HTTP Cache-Control header accordingly. Default is true.
- **serverTokens:** The content of the Server: HTTP header returned by dnsmdist. Default: *h2o/dnsmdist*
- **sessionTimeout:** Set the TLS session lifetime in seconds, this is used both for TLS ticket lifetime and for sessions kept in memory.
- **sessionTickets:** Whether session resumption via session tickets is enabled. Default: true (ie: tickets are enabled)
- **tcpFastOpenQueueSize:** Set the TCP Fast Open queue size, enabling TCP Fast Open when available and the value is larger than 0.
- **tcpListenQueueSize:** Set the size of the listen queue.
- **trustForwardedForHeader:** Whether to parse any existing X-Forwarded-For header in the HTTP query and use the right-most value as the client source address and port, for ACL checks, rules, logging and so on. Default is false.
- **responses** (Responses to URLs in *urls* which should not be a DNS answer, but a custom HTTP response)
 - **regex:** Regular expression to match the path against
 - **status:** HTTP code to answer with
 - **content:** Content of the HTTP response (or a URL in case of a redirect - HTTP-3XX)
 - **headers:** Dictionary of HeaderName:HeaderValue pairs to add to each response (Omitted on redirect responses)
- **certificates** (List of certificates to be used on the DoH listener)
 - **cert:** Certificate in PEM format, including intermediates if applicable
 - **key:** Private key corresponding to the certificate

9.2.5 DNS over TLS

doh (List of configurations of DoT listeners)

- **name:** Name of the DoT listener (used for naming the corresponding Service objects, etc)
- **locals:** Amount of listen sockets per dnstest pod (default: 1)
- **secrets:** List of names of Secrets (Type: kubernetes.io/tls) containing certificates & keys to be used on the DoT listener. Key must be in *tls.key* node and certificate (+ intermediates if applicable) must be in *tls.crt* node.
- **service:** Configuration of the Kubernetes service object (Note: See the section 'Exposing dnstest' for more details and examples on how to configure this)
- **stekSecret:** Name of a Secret (Type: Opaque) with stek tickets included in the *tickets* node. This secret is monitored for changes and will be updated in dnstest whenever a change is detected. Default: CloudControl will generate and update tickets as per the defaults (See parameters named stek* in the dnstest defaults section)
- **config** (Configuration options for the DoT listener)
 - **ciphers:** The TLS ciphers to use, in OpenSSL format. Ciphers for TLS 1.3 must be specified via ciphersTLS13.
 - **ciphersTLS13:** The TLS ciphers to use for TLS 1.3, in OpenSSL format.
 - **enableRenegotiation:** Whether secure TLS renegotiation should be enabled. Default: false (Disabled by default since it increases the attack surface and is seldom used for DNS)
 - **maxConcurrentTCPConnections:** Maximum number of concurrent incoming TCP connections. Default: 0 (which means unlimited).
 - **maxInFlight:** Maximum number of in-flight queries. The default is 0, which disables out-of-order processing.
 - **minTLSVersion:** Minimum version of the TLS protocol to support. Possible values are *tls1.0* *tls1.1*, *tls1.2* and *tls1.3*. Default is to require at least TLS 1.0.
 - **numberOfStoredSessions:** The maximum number of sessions kept in memory at the same time. Default is 20480. Setting this value to 0 disables stored session entirely.
 - **preferServerCiphers:** Whether to prefer the order of ciphers set by the server instead of the one set by the client. Default is true, meaning that the order of the server is used.
 - **releaseBuffers:** Whether OpenSSL should release its I/O buffers when a connection goes idle, saving roughly 35 kB of memory per connection. Default: true
 - **sessionTimeout:** Set the TLS session lifetime in seconds, this is used both for TLS ticket lifetime and for sessions kept in memory.
 - **sessionTickets:** Whether session resumption via session tickets is enabled. Default: true (ie: tickets are enabled)
 - **tcpFastOpenQueueSize:** Set the TCP Fast Open queue size, enabling TCP Fast Open when available and the value is larger than 0.
 - **tcpListenQueueSize:** Set the size of the listen queue.

- **certificates** (List of certificates to be used on the DoT listener)
 - **cert**: Certificate in PEM format, including intermediates if applicable
 - **key**: Private key corresponding to the certificate

9.3 recursors

Configuration of recursor instances

Key: name (Name of the recursor instance)

9.3.1 Parameters

- **affinity**: Kubernetes pod affinity
- **antiAffinityPreset**: Pod anti affinity preset (Accepted values: *preferred* or *required*)
- **hostNetwork**: Use host networking for recursor pods
- **inboundInterfaces**: List of names of interfaces to which recursor will bind
- **luaConfig**: Lua configuration to be included in each recursor pod (See 'Overview' document for usage examples)
- **luaScript**: Lua script to be included in each recursor pod (See 'Overview' document for usage examples)
- **metricsInterfaces**: List of names of interfaces to which the metrics aggregator will bind
- **nodeSelector**: Kubernetes pod nodeSelector
- **outboundInterfaces**: List of names of interfaces from which recursor will try to send outbound traffic
- **podAnnotations**: Annotations to be added to each Pod
- **podLabels**: Labels to be added to each Pod
- **podSecurityContext**: Kubernetes Pod security context (default: 953 as fsGroup, runAsUser & runAsGroup)
- **replicas**: Default number of replicas in a recursor deployment (default: 2)
- **revisionHistoryLimit**: Default 'revisionHistoryLimit' for recursor deployments (default: 0)

9.3.2 Parameter Sets

- **dnsdist** (Settings to be applied to each recursor instance when added to dnsdist as a server)
 - **addXPF**: Add the client's IP address and port to the query, along with the original destination address and port. Default is disabled (0)
 - **checkClass**: Number to use as QCLASS in the health-check query, default is DNSClass.IN

- **checkInterval:** The time in seconds between health checks
- **checkName:** String to use as QNAME in the health-check query, default is "a.root-servers.net."
- **checkTimeout:** The timeout (in milliseconds) of a health-check query, default to 1000 (1s)
- **checkType:** String to use as QTYPE in the health-check query, default is "A"
- **disableZeroScope:** Disable the EDNS Client Subnet 'zero scope' feature, which does a cache lookup for an answer valid for all subnets (ECS scope of 0) before adding ECS information to the query and doing the regular lookup. This requires the *parseECS* option of the corresponding cache to be set to true
- **maxCheckFailures:** Allow this amount of check failures before declaring the backend down, default is 1
- **mustResolve:** Set to true when the health check MUST return a RCODE different from NXDomain, ServFail and Refused. Default is false, meaning that every RCODE except ServFail is considered valid
- **order:** The order of servers in this set, used by the *leastOutstanding* and *firstAvailable* policies
- **qps:** Limit the number of queries per second to this amount, when using the *firstAvailable* policy
- **reconnectOnUp:** Close and reopen the sockets when a server transits from Down to Up. This helps when an interface is missing when dnssdist is started. Default is false
- **retries:** The number of TCP connection attempts to servers in this set, for a given query
- **rise:** Require NUM consecutive successful checks before declaring the backend up, default is 1
- **setCD:** Set the CD (Checking Disabled) flag in the health-check query, default is false
- **sockets:** Number of sockets (and thus source ports) used toward the backend server, defaults to 1
- **source:** Name of the interface which Dnsdist will use to try to send traffic to this Recursor
- **tcpConnectTimeout:** The timeout (in seconds) of a TCP connection attempt
- **tcpFastOpen:** Whether to enable TCP Fast Open
- **tcpRecvTimeout:** The timeout (in seconds) of a TCP read attempt
- **tcpSendTimeout:** The timeout (in seconds) of a TCP write attempt
- **useClientSubnet:** Add the client's IP address in the EDNS Client Subnet option when forwarding the query to this backend
- **useProxyProtocol:** Add a proxy protocol header to the query, passing along the client's IP address and port along with the original destination address and port. Default is false

- **weight:** The weight of servers in this set, used by the *wrandom*, *whashed* and *chashed* policies, default is 1
- **config** (Recursor configuration, any configuration item listed in the recursor documentation (<https://doc.powerdns.com/recursor/settings.html>) can be referenced here. Settings which are explicitly ignored due to conflicts with Cloud Control are filtered by 'web-server*', 'local*', 'disable-syslog', 'daemon', 'cpu-map', 'chroot', 'socket*' and 'config*')
- **hpa** (Horizontal Pod Autoscaler - see helm values 'recursor.hpa' for examples)
 - **enabled:** Enable or disable the HPA (default: *false*)
 - **minReplicas:** Minimum # of replicas (default: 2)
 - **maxReplicas:** Maximum # of replicas (default: 4)
 - **metrics:** Metric(s) upon which to make decisions regarding scaling. Must be an array of MetricSpec (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#metricspec-v2beta2-autoscaling>). Examples are in the helm values.
 - **behavior:** Behavior of the HPA, must be instance of HorizontalPodAutoscalerBehavior (<https://kubernetes.io/docs/reference/generated/kubernetes-api/v1.22/#horizontalpodautoscalerspec-v2beta2-autoscaling>).
- **readiness** (Readiness probe Configuration)
 - **bindInterfaces:** List of names of interfaces to which the readiness probe will bind
- **resources** (recursor resource allocation defaults)
 - **limits** (Limit amounts)
 - * **cpu:** Limit amount of CPU (Kubernetes default)
 - * **memory:** Limit amount of memory (Kubernetes default)
 - **requests** (Request amounts)
 - * **cpu:** Request amount of CPU (Kubernetes default)
 - * **memory:** Request amount of memory (Kubernetes default)

9.3.3 Forward Zones

forward (List of sets of zones to be forwarded to Auth instances, Recursor instances or other resolvers)

- **exclude:** If *learnFrom* is configured, exclude any zones which match this list of regular expressions (this is processed after the *include* filter)
- **include:** If *learnFrom* is configured, include only zones which match this list of regular expressions (this is processed before the *exclude* filter)
- **learnFrom:** Name of a set of Auth instances from which forward zones must be learned (can be filtered using *include* and/or *exclude*)
- **nta:** Add a negative trust anchor for the forwarded zones (default: *false*)
- **recurse:** Set the recursion desired (RD) bit to 1 for the forwarded zones (default: *false*)
- **zones:** List of zones to be forwarded (not affected by *include* and *exclude*)

- **serverGroups:** (List of server groups to forward to - Auth, Recursor or Resolver instances)
 - **group:** Name of the group of instances

9.4 resolvers

Configuration of external resolvers

Key: name (Name of the resolver instance)

9.4.1 Parameters

- **ips:** List of IP addresses of resolver endpoints
- **port:** Port to send traffic to for resolver endpoints

9.4.2 Parameter Sets

- **dnsdist** (Settings to be applied to each resolver instance when added to dnsdist as a server)
 - **addXPF:** Add the client's IP address and port to the query, along with the original destination address and port. Default is disabled (0)
 - **checkClass:** Number to use as QCLASS in the health-check query, default is DNSClass.IN
 - **checkInterval:** The time in seconds between health checks
 - **checkName:** String to use as QNAME in the health-check query, default is "a.root-servers.net."
 - **checkTimeout:** The timeout (in milliseconds) of a health-check query, default to 1000 (1s)
 - **checkType:** String to use as QTYPE in the health-check query, default is "A"
 - **disableZeroScope:** Disable the EDNS Client Subnet 'zero scope' feature, which does a cache lookup for an answer valid for all subnets (ECS scope of 0) before adding ECS information to the query and doing the regular lookup. This requires the *parseECS* option of the corresponding cache to be set to true
 - **maxCheckFailures:** Allow this amount of check failures before declaring the back-end down, default is 1
 - **mustResolve:** Set to true when the health check MUST return a RCODE different from NXDomain, ServFail and Refused. Default is false, meaning that every RCODE except ServFail is considered valid
 - **order:** The order of servers in this set, used by the *leastOutstanding* and *firstAvailable* policies
 - **qps:** Limit the number of queries per second to this amount, when using the *firstAvailable* policy

- **reconnectOnUp**: Close and reopen the sockets when a server transits from Down to Up. This helps when an interface is missing when dnsmasq is started. Default is false
- **retries**: The number of TCP connection attempts to servers in this set, for a given query
- **rise**: Require NUM consecutive successful checks before declaring the backend up, default is 1
- **setCD**: Set the CD (Checking Disabled) flag in the health-check query, default is false
- **sockets**: Number of sockets (and thus source ports) used toward the backend server, defaults to 1
- **source**: Name of the interface which Dnsmasq will use to try to send traffic to this external resolver
- **tcpConnectTimeout**: The timeout (in seconds) of a TCP connection attempt
- **tcpFastOpen**: Whether to enable TCP Fast Open
- **tcpRecvTimeout**: The timeout (in seconds) of a TCP read attempt
- **tcpSendTimeout**: The timeout (in seconds) of a TCP write attempt
- **useClientSubnet**: Add the client's IP address in the EDNS Client Subnet option when forwarding the query to this backend
- **useProxyProtocol**: Add a proxy protocol header to the query, passing along the client's IP address and port along with the original destination address and port. Default is false
- **weight**: The weight of servers in this set, used by the *wrandom*, *whashed* and *chashed* policies, default is 1

9.5 rulesets

Rulesets allow for the configuration of dnsmasq Packet Policies. For a detailed example of how to use these rulesets, please refer to the *Getting Started* chapter in the *Overview* guide.

A basic ruleset looks as follows:

```
rulesets:
  tcp-refusal-ruleset:
    group: block-traffic
    type: DNSDistRule
    priority: 100
    rules:
      - name: Refuse TCP
        combinator: AND
        selectors:
          - TCP: true
          - QName: "tcptrue.example.com"
    action:
      RCode:
        rcode: "REFUSED"
```

Where 'tcp-refusal-ruleset' is the name of the ruleset, which will be used to create a uniquely named object. Under this name, the ruleset is defined, using the following values:

- **group:** The value of this parameter can be referenced in a dnsmdist configuration to apply the rules from this ruleset to that instance
- **type:** Type of ruleset, currently limited to 'DNSDistRule'
- **priority:** Priority of this ruleset. If multiple are assigned to a dnsmdist instance, it will process the rule with the lowest 'priority' value first.
- **rules:** An array of rules to be applied to this ruleset (see below for more details on rules)

9.5.1 Rules

Rules are configurable via 4 different parameters:

- **name:** Name of the rule
- **combinator:** One of 'AND', 'OR' or 'NOT'
- **selectors:** List of filters on which to apply the logic of the combinator
- **action:** Action to apply to the traffic selected by the above selectors

As a result, a single rule will look as follows:

```
name: Refuse TCP
combinator: AND
selectors:
  - TCP: true
  - QName: "tcptrue.example.com"
action:
  RCode:
    rcode: "REFUSED"
```

9.5.2 Combinators

The available combinators function as follows:

- **AND:** If all selectors match, the action will be applied
- **OR:** If any of the selectors match, the action will be applied
- **NOT:** If the selector does not match, the action will be applied (Only 1 selector is allowed when using a NOT combinator)

9.5.3 Selectors

The following selectors are available:

9.5.3.1 TCP

Format:

```
TCP: true
```

If 'true', this will select queries received over TCP. If 'false' it will select non-TCP traffic (ie: UDP)

9.5.3.2 MaxQPS

Format:

```
MaxQPS:  
qps: 50
```

Matches traffic not exceeding this qps limit. If e.g. this is set to 50, starting at the 51st query of the current second traffic stops being matched. This can be used to enforce a global QPS limit.

9.5.3.3 MaxQPSIP

Format:

```
MaxQPSIP:  
qps: 20  
v4Mask: 32  
v6Mask: 64  
burst: 20  
expiration: 300  
cleanupDelay: 60  
scanFraction: 10
```

Explanation of each parameter:

- qps (int) – The number of queries per second allowed, above this number traffic is matched
- v4Mask (int) – The IPv4 netmask to match on. Default is 32 (the whole address)
- v6Mask (int) – The IPv6 netmask to match on. Default is 64
- burst (int) – The number of burstable queries per second allowed. Default is same as qps
- expiration (int) – How long to keep netmask or IP addresses after they have last been seen, in seconds. Default is 300
- cleanupDelay (int) – The number of seconds between two cleanups. Default is 60
- scanFraction (int) – The maximum fraction of the store to scan for expired entries, for example 5 would scan at most 20% of it. Default is 10 so 10%

Since most of the parameters have defaults, you can define a basic MaxQPSIP selector as follows:


```
MaxQPSIP:  
  qps: 20
```

9.5.3.4 NetmaskGroup

Format:

```
NetmaskGroup:  
  nmg:  
  - "192.0.2.0/28"  
  - "2001:db8:1234::/64"  
  src: true  
  quiet: false
```

Explanation of each parameter:

- nmg (NetMaskGroup) – The NetMaskGroups to match on
- src (bool) – Whether to match source or destination address of the packet. Defaults to true (matches source)
- quiet (bool) – Do not display the list of matched netmasks in Rules. Default is false.

Since most of the parameters have defaults, you can define a basic NetmaskGroup selector as follows:

```
NetmaskGroup:  
  nmg:  
  - "192.0.2.0/28"  
  - "2001:db8:1234::/64"
```

9.5.3.5 Opcode

Format:

```
Opcode: "Notify"
```

This selector matches queries with the specified opcode exactly. An example usecase for this selector is to route zone update notification queries to secondary Auth instances, ie:

```
name: authnotify  
combinator: AND  
selectors:  
  - Opcode: "Notify"  
action:  
  Pool:  
    poolname: "auth"
```

9.5.3.6 QName

Format:

```
QName: "host.example.com"
```

This selector matches queries with the specified qname exactly.

9.5.3.7 QType

Format:

```
QType: "SOA"
```

This selector matches queries with the specified qtype exactly. An example usecase for this selector is to route zone transfer related queries to Auth instances, ie:

```
name: authxfr
combinator: OR
selectors:
  - QType: "SOA"
  - QType: "AXFR"
  - QType: "IXFR"
action:
  Pool:
    poolname: "auth"
```

9.5.4 Actions

The following actions are available:

9.5.4.1 Allow

Format:

```
Allow: true
```

Let these packets go through.

9.5.4.2 Drop

Format:

```
Drop: true
```

Drop the packet.

9.5.4.3 Pool

Format:

```
Pool:  
  poolname: "name-of-a-pool"
```

The Pool action will send the packet into the specified pool

9.5.4.4 QPS

Format:

```
QPS:  
  maxqps: 10
```

Drop a packet if it does exceed the maxqps queries per second limits.

9.5.4.5 RCode

Format:

```
RCode:  
  rcode: "REFUSED"
```

The RCode action will answer any selector queries with the rcode specified.

9.5.4.6 TC

Format:

```
TC: true
```

Create answer to query with the TC bit set, and the RA bit set to the value of RD in the query, to force the client to TCP.

9.6 zonecontrols

Configuration of zonecontrol instances

Key: name (Name of the zonecontrol instance)

9.6.1 Parameters

- **affinity**: Kubernetes pod affinity
- **antiAffinityPreset**: Pod anti affinity preset (Accepted values: *preferred* or *required*)
- **hostNetwork**: Use host networking for zonecontrol pods
- **ingress**: Ingress object to expose the zonecontrol endpoint via an ingress managed by an ingress controller (For formatting example, see the *Exposing auth API* chapter)
- **nodeSelector**: Kubernetes pod nodeSelector
- **postgres**: Postgres database configuration (See: *Postgres Database* chapter below for details)
- **replicas**: Default number of replicas in a auth deployment (default: 2)
- **service**: Service object to expose the zonecontrol endpoint (For formatting example, see the *Exposing dnsmdist* chapter, which covers the *service* format to add ClusterIP, NodePort or LoadBalancer services)

9.6.2 Parameter Sets

- **authEndpoints** (Configuration of authoritative DNS server API endpoints)
 - **name**: Name of the endpoint (If there are multiple endpoints, the name of endpoints must be unique)
 - **url**: URL of the API endpoint (Including protocol, port)
 - **key**: API key to authenticate against the endpoint
- **resources** (zonecontrol resource allocation defaults)
 - **limits** (Limit amounts)
 - * **cpu**: Limit amount of CPU (Kubernetes default)
 - * **memory**: Limit amount of memory (Kubernetes default)
 - **requests** (Request amounts)
 - * **cpu**: Request amount of CPU (Kubernetes default)
 - * **memory**: Request amount of memory (Kubernetes default)

9.6.3 Postgres Database

ZoneControl requires a Postgres database to run. You can either specify the details of an existing database or have the bundled Postgres Operator create one. Both options are described in further detail below.

9.6.3.1 Postgres (pre-existing)

If you have an existing Postgres database available, you can configure a zonecontrol instance to utilize it. Configuring a pre-existing Postgres database can be done via the following configuration:

Format:

```
postgres:  
  host: host-of-postgres-cluster  
  dbname: auth  
  user: some_user  
  password: some_user_password
```

Available parameters:

- host - Host of the Postgres cluster/service
- port - Port over which to access the Postgres database (Optional, default: 5432)
- dbname - Name of the database
- user - User with which to connect
- password - Password for *user*
- sslmode - Postgres *sslmode* to use while connecting (Optional, omitted if no value is provided)

9.6.3.2 Postgres (Operator-managed)

If you have deployed the postgres-operator chart to your Kubernetes cluster, you can configure a zonecontrol instance to use a operator-managed Postgres database. Configuring such a Postgres database can be done via the following configuration:

Format:

```
postgres:  
  operator: true
```

Available parameters:

- operator - Must be set to *true*

The Postgres database which is created utilizes the default values which are exposed via the helm values in *zonecontrol.postgres*.

10 Prometheus

This section allows you to configure 2 forms of Prometheus scraping configurations:

- Via PodMonitor objects (if a Prometheus Operator) is available
- Via Prometheus scraping annotations on Pods

By default, all Pods will have the following annotations present for Prometheus scraping:

- `prometheus.io/path` = the path where the metrics endpoint serves metrics (default: `/metrics`)
- `prometheus.io/port` = the port to which the metrics endpoint listens (default: `8082`)
- `prometheus.io/scheme` = the scheme for serving metrics (default: `http`)
- `prometheus.io/scrape` = whether or not to scrape this endpoint (default: `true`)

To disable this default behavior, you can set the value `prometheus.annotations` to `false` (default: `true`)

If you have a Prometheus Operator available or if you deployed the stack including the *Monitoring Operators* chart, you can set the value `prometheus.operator.available` to `true` (default: `false`). As a result PodMonitor objects will be created for each `dnsdist` & `recursor` instance, with all the necessary scraping details automatically included. These pods should then all be discovered automatically by the Prometheus Operator.