



Release Notes for Patch Release #6101
2022-03-02

Copyright notice

©2022 by OX Software GmbH. All rights reserved. Open-Xchange and the Open-Xchange logo are trademarks or registered trademarks of OX Software GmbH. All other company and/or product names may be trademarks or registered trademarks of their owners. Information contained in this document is subject to change without notice.

1 Shipped Product and Version

Open-Xchange App Suite backend 7.10.5-rev39
Open-Xchange App Suite frontend 7.10.5-rev31

Find more information about product versions and releases at http://oxpedia.org/wiki/index.php?title=AppSuite:Versioning_and_Numbering and <http://documentation.open-xchange.com/>.

2 Bugs fixed since previous Public Release

This section provides a summary of bug fixes and changes that have been applied subsequently to shipping Patch Release #6092.

MWB-1448 Compose is moved to trash if "com.openexchange.mail.compose.maxSpacesPerUser" is over

Max. number of composition spaces not orderly considered when opening a new one.
This has been solved by Considering max. number of composition spaces when opening a new one.

OXUIB-1262 Single quote in mail compose To field handled incorrectly

This wasn't considered yet.
This has been solved by extending the regex.

MWB-1439 Need to extend log to analyze "Found no such resource in attachment storage for identifier: undefined" errors

Extend log to get more infos.

MWB-1387 gdpr data export fails reliably

Errors while trying to resume a previously paused data export.
Solution: Handle possible connect failure while exporting mails. Avoid pausing running data export tasks. Let started ones complete and avoid unnecessarily stopping data export tasks in case a continuous timeframe is configured, e.g. "com.openexchange.gdpr.dataexport.schedule=Mon-Sun".

MWB-1413 Birthday calendar name is changeable via DAV but not in Web UI

Update of DAV:displayname property permitted through CalDAV for default Birthdays calendar.
Treat DAV:displayname property as protected for Birthdays calendar, and indicate forbidden property updates via DAV:cannot-modify-protected-property precondition.

MWB-1423 Context taxonomy not mentioned in cli onlinehelp

Missing help text for dynamic options.
This has been fixed by adding a help text for dynamic options.

MWB-1435 Errors on the conversion layer API used by mobile applications

Parse errors if a MIME message contains a corrupt Content-Type string.
This has been fixed by sanitizing Content-Type string in case a corrupt one is present in MIME message or one of its parts.

3 Changes relevant for Operators

3.1 Changes of Configuration Files

Change #SCR-1001 Added new options to override STARTTLS setting for iOS/PLIST profiles

Added new lean options to override STARTTLS setting for iOS/PLIST profiles:

- `com.openexchange.client.onboarding.mail.imap.requireTls`
Specifies whether STARTTLS is required to established to access the IMAP server. If not set,

falls-back to internal settings for accessing the primary account.

- `com.openexchange.client.onboarding.mail.smtp.requireTls`
Specifies whether STARTTLS is required to established to access the SMTP server. If not set, falls-back to internal settings for accessing the primary account.

Change #SCR-997 Added new property to control whether pause&resume is applied to data export tasks

Added new lean property "`com.openexchange.gdpr.dataexport.allowPausingRunningTasks`" to control whether pause&resume is applied to data export tasks. Default value is false. Neither reload-able nor config-cascade aware.

4 Tests

Not all defects that got resolved could be reproduced within the lab. Therefore, we advise guided and close monitoring of the reported defect when deploying to a staging or production environment. Defects which have not been fully verified, are marked as such.

To avoid side effects, the shipped packages have gone through automated regression test on both, a Continuous Integration System and a dedicated server set-up for system and integration testing. All changes have been checked for potential side-effects and effect on behavior. Unless explicitly stated within this document, we do not expect any side-effects.

5 Fixed Bugs

MWB-1448, OXUIB-1262, MWB-1439, MWB-1387, MWB-1413, MWB-1423, MWB-1435,