



Release Notes for Patch Release #6026
2021-08-23

Security Patch Release

This Patch Release addresses critical vulnerabilities; please consider deploying it as soon as possible. Not deploying this Patch Release may result in remote service exploitation, security threats to users and exposure of sensitive data.

Detailed vulnerability descriptions will be publicly disclosed no earlier than fifteen (15) working days after public availability of this Patch Release. There is no indication that one or more of these vulnerabilities are already getting exploited or that information about them is publicly circulating.

Copyright notice

©2021 by OX Software GmbH. All rights reserved. Open-Xchange and the Open-Xchange logo are trademarks or registered trademarks of OX Software GmbH. All other company and/or product names may be trademarks or registered trademarks of their owners. Information contained in this document is subject to change without notice.

1 Shipped Product and Version

Open-Xchange App Suite backend 7.10.5-rev21
Open-Xchange App Suite frontend 7.10.5-rev18

Find more information about product versions and releases at http://oxpedia.org/wiki/index.php?title=AppSuite:Versioning_and_Numbering and <http://documentation.open-xchange.com/>.

2 Vulnerabilities fixed since previous Public Release

This section provides a summary of bug fixes and changes that have been applied subsequently to shipping Patch Release #6020. Solutions for vulnerabilities have been provided for the existing code-base via Patch Releases.

OXUIB-872 CVE-2021-38374
CVSS:3.1

MWB-1113 CVE-2021-38375
CVSS:3.1

MWB-1116 CVE-2021-38377
CVSS:3.1

3 Bugs fixed since previous Public Release

This section provides a summary of bug fixes and changes that have been applied subsequently to shipping Patch Release #6020.

OXUIB-948 File en_SG.js renamed to en_sg.js in package open-xchange-appsuite
Moment renamed en-SG to en-sg.
This has been solved by updating the locale lookup table to new filename.

OXUIB-920 "locked" view during running GDPR Export is wrong
When redrawing the default configuration was used all the time.
This has been fixed by only using default configuration when no download is pending. Show requested modules instead.

MWB-667 Mail filter apply does not work for copy
The copy require was missing from the FILEINTO action command, hence the MailFilterService was generating the wrong require directive for the sieve script. The issue lies within the MailFilterService.getFilterRule when the method reconstructs the Rule object from the sieve script, i.e. the copy require is not added as an optional require.
This has been solved by including the copy as an optional require for the FILEINTO action command.

OXUIB-932 Draft autoloading on mobile causes huge amount of "draft changed in another tab" messages
This was caused by immediate loading of drafts on mobile.
This has been solved by introducing lazyload for mobile devices.

OXUIB-917 Several "No such job" error messages for some customers (increasing) after update to 7.10.5
UI did not check for error codes and kept requesting long running jobs.
This has been fixed by removing jobs from queue for error code JOB-0002 so they are not requested anymore.

OXUIB-884 Onboarding Wizard "Connect Your Device" not correctly displayed on small iOS Displays

Flex shrink was behaving strangely for small devices.
This has been resolved by removing shrink for some components.

OXUIB-931 Default rights when sharing a folder to an unnamed user are "Author"

Since the redesign the default was set to author right for folders and viewer rights for files.
Solution: Changed it to default to viewer rights in all cases.

4 Tests

Not all defects that got resolved could be reproduced within the lab. Therefore, we advise guided and close monitoring of the reported defect when deploying to a staging or production environment. Defects which have not been fully verified, are marked as such.

To avoid side effects, the shipped packages have gone through automated regression test on both, a Continuous Integration System and a dedicated server set-up for system and integration testing. All changes have been checked for potential side-effects and effect on behavior. Unless explicitly stated within this document, we do not expect any side-effects.

5 Fixed Bugs

OXUIB-948, OXUIB-920, MWB-667, OXUIB-932, OXUIB-917, OXUIB-884, OXUIB-931, OXUIB-872, MWB-1113, MWB-1116,